

Sender25 - Instalação WHM - EXIM

Precisamos ajustar 3 campos para que o EXIM no WHM para que funcione corretamente, localizado em

Configurações e Serviços -> Gerenciar as configurações de EXIM -> Advancer Editor

Section: POSTMAILCOUNT

```
send_via_sender25:
  driver = manualroute
  .ifdef SRSENABLED
    transport = ${if eq {$local_part{$domain} \
    {$original_local_part{$original_domain} \
    {sender25_smtp} {sender25_forward_smtp}}
  .else
    transport = sender25_smtp
  .endif
  domains = ! +local_domains
  hosts_randomize = true
  route_list = * smtp-a.sender25.com::25 randomize byname
  host_find_failed = defer
  no_more
```

Você pode usar o servidor smtp-a.sender25.com porta 25 ou smtp-b.sender25.com porta 2525

Section: TRANSPORTSTART

```
dsn_direct_smtp:
  driver = smtp
  message_linelength_limit = 1000000
```

```

sender25_smtp:
driver = smtp
    hosts_require_auth = *
    tls_tempfail_tryclear = true
    headers_add = "x-authuser: ${if def:authenticated_id\
    ${if
match{$authenticated_id}{.*@.*}{$authenticated_id}{$authenticated_id@$primary_hostname}}}\
    ${if
and{{eq{$received_protocol}{local}}{def:sender_ident}}{$sender_ident@$primary_hostname}{}}}\n
\
    X-Authenticated-Id: ${if def:authenticated_id\
    ${if
match{$authenticated_id}{.*@.*}{$authenticated_id}{$authenticated_id@$primary_hostname}}}\
    ${if
and{{eq{$received_protocol}{local}}{def:sender_ident}}{$sender_ident@$primary_hostname}{}}}"
    dkim_domain = $sender_address_domain
    dkim_selector = default
    dkim_canon = relaxed
    dkim_private_key = "/var/cpanel/domain_keys/private/${dkim_domain}"
    message_linelength_limit = 1000000

.ifdef SRSEENABLED
    sender25_forward_smtp:
        driver = smtp
        hosts_require_auth = *
        max_rcpt = 1
        return_path = ${srs_encode {SRS_SECRET} {$return_path} {$original_domain}}
        tls_tempfail_tryclear = true
        headers_add = "X-AuthUser: ${if def:authenticated_id\
        ${if
match{$authenticated_id}{.*@.*}{$authenticated_id}{$authenticated_id@$primary_hostname}}}\
        ${if
and{{eq{$received_protocol}{local}}{def:sender_ident}}{$sender_ident@$primary_hostname}{}}}\n
\
        X-Authenticated-Id: ${if def:authenticated_id\
        ${if
match{$authenticated_id}{.*@.*}{$authenticated_id}{$authenticated_id@$primary_hostname}}}\
        ${if
and{{eq{$received_protocol}{local}}{def:sender_ident}}{$sender_ident@$primary_hostname}{}}}"
        dkim_domain = $sender_address_domain

```

```
dkim_selector = default
dkim_canon = relaxed
dkim_private_key = "/var/cpanel/domain_keys/private/${dkim_domain}"
endif
```

Section: AUTH

```
auth_login:
  driver = plaintext
  public_name = LOGIN
  #specify your mailchannels SMTP user and password below
  hide client_send = : USUARIO : ${lookup{sender25}lsearch{/etc/exim.sender25.auth}}
```

Criar arquivo de senha externo no arquivo

```
/etc/exim.sender25.auth
```

Conteúdo:

```
sender25: SenhaSMTP
```

Ou alterar de um usuário já existente.

```
printf 'sender25: %s\n' \
"$(sed -n 's|^[[:space:]]*client_send = : "Mudar Usuario" : ||p' /etc/exim.conf.local)" \
> /etc/exim.sender25.auth
chown root:mail /etc/exim.sender25.auth
chmod 640 /etc/exim.sender25.auth
```

Alterar USUARIO por ORGANIZACAO/NOMEDOSERVER que vem do Sender25
Alterar SENHA pela chave SMTP gerada no painel do sender

É necessário liberar o ip do sender25 no Firewall

Neste exemplo nós utilizamos o host smtp-a.sender25.net e smtp-b.sender25.net, sendo 170.247.61.197 e 170.247.61.198

Adicionar ip do servidor Sender a lista de ips liberados.

Liberar IP no Firewall

```
csf -a 170.247.61.197 sender25
csf -a 170.247.61.198 sender25
```

Restart Firewall

```
csf -r
```

Revision #2

Created 2026-09-15 11:51:53 UTC by Ewerton Henrique

Updated 2026-09-15 11:55:48 UTC by Ewerton Henrique